




Using the VAMPIRE Data Converter

Installation

- ▶ VAMPIRE source:
<https://github.com/richard-evans/vampire.git>
Use “develop” branch
- ▶ In terminal:
`make vdc`
- ▶ The vdc executable can then be found at:
`.../vampire/util/vdc/vdc`

The Manual

- ▶ Included in the source under
.../vampire/manual/vampire-manual.tex
- ▶ A LaTeX file must be compiled into a pdf



Displaying Atomic positions

- ▶ Requires input file parameter:
`config:atoms`
- ▶ This must be included before running the simulation
 - ▶ New files: data and meta files
- ▶ Run vdc:
`util/vdc/vdc -xyz`
 - ▶ New file: `crystal.xyz`
- ▶ Use a `.xyz` file viewer such as Jmol or VESTA

Customisation and Troubleshooting

- ▶ VDC should also be used to check inputs
- ▶ Using slices
 - ▶ `--slice [xmin, xmax, ymin, ymax, zmin, zmax]`
 - ▶ Parameters are in fractional coordinates
- ▶ Removing materials
 - ▶ `--remove-material [material1,material2,...]`
 - ▶ *Material numbers correspond to those in material file*
- ▶ *More options are explained in the Manual*

Displaying Spins in POV-Ray

- ▶ Initial requirements:
 - ▶ Use `config:atoms`
 - ▶ POV-Ray installation
 - ▶ Ubuntu: `sudo apt install povray`
 - ▶ Otherwise find binaries at <http://povray.org/download/>
- ▶ Run vdc:
 - ▶ `utils/vdc/vdc --povray`
 - ▶ Several new files: `.inc .ini .pov`

POV-Ray Customisation

- The spins.pov file:

```
//-----  
// Povray file generated using vampire  
//-----  
#version 3.5;  
#include "colors.inc"  
#include "metals.inc"  
#include "screen.inc"  
#declare LX=0.0;  
#declare LY=0.0; Look at Position  
#declare LZ=0.0;  
#declare CX=300.008;  
#declare CY=600.005; Camera Position  
#declare CZ=150.006;  
#declare ref=0.05;  
global_settings { assumed_gamma 2.0 }  
background { color Gray30 }  
Set_Camera(<CX,CY,CZ>, <LX,LY,LZ>, 15) Camera Angle  
Set_Camera_Aspect(4,3)  
Set_Camera_Sky(<0,0,1>)
```

Displaying Spins in POV-Ray


- ▶ To run povray:
`povray -w3600 -h2700 +A0.3 spins`
- ▶ `-w` and `-h` choose the image width and height (resolution) and `+A0.3` uses antialiasing.
- ▶ The `spins.pov` file contains additional options

POV-Ray Customisation

- ▶ Command line parameters:
 - ▶ `--vector-z [x,y,z]` to change primary axis
 - ▶ `--colourmap [name]` to change palette
- ▶ Some colourmaps lend themselves better to different systems
 - ▶ For Vortex systems try “C2”

POV-Ray Colourmaps

- ▶ Default: Red-White-Blue-White-Red



- ▶ Other options:

- ▶ For vortex: C2

